

## Editmote 1.1.1



### User Manual

Editmote is an iPhone and iPod Touch remote control for Final Cut Pro, Final Cut Pro X, Avid Media Composer, Adobe Premiere Pro, Adobe After Effects and QuickTime Player for Mac.

Operate the playhead, add markers, set in and out points and adjust the volume - all from the comfort of your screening room couch.

Editmote is an essential tool for editors that simplifies screening your project.

#### **What's new in this version (1.1.1)**


- Added an option to disable feedback when adjusting system volume remotely
- General bug fixes, tweaks and improvements

## Contents


Installation.....	3
Button Customization.....	5
Advanced Options .....	6
<b>Security Settings</b> .....	<b>8</b>
Keyboard Layouts.....	9
Frequently Asked Questions.....	11
<i>Q: Why can't I see my computer name in the list? .....</i>	<i>11</i>
<i>Q: Why do some of the buttons appear to do nothing?.....</i>	<i>11</i>
<i>Q: Why is it not playing back when I press Play?.....</i>	<i>11</i>
<i>Q: Why is Editmote is telling me to update the app or the preference pane? .....</i>	<i>11</i>
Support .....	12

## Installation

1. Download the Editmote Preference Pane from <http://www.digitalrebellion.com/editmote> onto your editing machine and double-click to install it.
2. Once the preference pane launches, put the switch in the On position.



3. Launch Editmote on your iOS device.
4. Select the name of your computer in the list.




5. Make sure Final Cut Pro, FCP X, Avid Media Composer, Adobe Premiere Pro, After Effects, QuickTime Player or VLC is running and use the controls to remotely operate the application.

Note that not every button is functional on every application - for example, QuickTime Player has no marker capabilities so the marker buttons do nothing when pressed while QuickTime Player is running.

## Button Customization

The default button layout can be customized by going to the Actions menu and tapping **Edit Button Layout**.


Tap a button to display a list of actions that you can change it to.



When complete, tap the **Done** button in the top right corner to finish editing.

## Advanced Options


Editmote may be unable to negotiate some corporate networks. For these situations, we recommend disabling Bonjour broadcasts in the Editmote Preference Pane and specifying a network interface and port to listen on.



After selecting these options, the Editmote preference pane will take a few seconds to reconnect and will then display the IP and port on the left-hand side under the Status section.

Launch Editmote on your iOS device, tap the Actions button in the top right and select **Manual IP**.

In the dialog that appears, type the IP address and port displayed in the Editmote preference pane and tap **Connect**.




Note: when you launch the preference pane it may take a few seconds before the IP and port appear in the Status section.

## Security Settings


By default, the Editmote preference pane will allow any iOS device to connect to it and remotely control the editing software on that system.

Ticking the option **Confirm before allowing a device to connect** will ask the user on the computer for permission before Editmote will be able to control that device.



## Keyboard Layouts

Editmote is set to use the default keyboard layout for your editing application. If you have customized your keyboard layout, the Keyboard Layouts tab in the preference pane allows you to modify the defaults to match your customized layout.



Select the application you wish to modify in the left-hand pane and the current keyboard shortcuts will appear in the right-hand pane. To modify a shortcut, double-click it or click the Edit button. When the popup appears at the top of the screen, hold down the new keyboard shortcut to set it.

To remove a shortcut completely, select it in the list and press the Delete or Backspace key.

Additional applications can be supported by clicking the + button at the bottom left of the window and browsing for the application you would like to support.

**Note:** If you are using a non-English language keyboard and find that Editmote does not recognize your button presses correctly, you will need to setup the keys to work with your keyboard. Edit each item one-by-one and press the corresponding keys on your keyboard, even if the correct key is already listed in the box. Once you have done this, Editmote will work correctly. Not every user with foreign language keyboards will need to do this.

## Frequently Asked Questions

**Q: Why can't I see my computer name in the list?**

A: Editmote only operates over wi-fi and your phone and Mac must be on the same network.

**Q: Why do some of the buttons appear to do nothing?**

A: Not all buttons are functional for every application. For example, the marker buttons don't work with QuickTime Player because QuickTime Player has no marker functionality.

Also, Editmote assumes that you are using the default keyboard layout unless you edit the layout in the preference pane.

**Q: Why is it not playing back when I press Play?**

A: You must ensure that the application is activated and that no dialog boxes have appeared (these can sometimes appear in another Space which can be confusing). In the case of Final Cut Pro, you must have either the viewer or timeline selected in order to successfully initiate playback.

**Q: Why is Editmote is telling me to update the app or the preference pane?**

A: Changes in newer versions of Editmote may require you to update the preference pane or Editmote app via iTunes before you can connect. The Editmote preference pane should be kept in sync with the Editmote app. Every time you install an Editmote update via iTunes, launch the preference pane and click the button to check for updates.

## Support

Bug reports and feature requests can be submitted using the **Leave Feedback** link in the Actions menu.

Crash reports are best submitted using the feedback link instead of through iTunes. Crash logs are located at `~/Library/Logs/CrashReporter/MobileDevice/[name of iPad]` and `~/Library/Logs/CrashReporter/MobileDevice/[name of iPad].symbolicated`.